

Scarecrow

Materials

Dk or sports acrylic yarn in the following colors: british racing green, orange, red, green, blue, maize-yellow, terracotta, brown, black and white.

C hook (2.5 mm), a tapestry needle, stuffing and scissors.

Stitches used in the project

Double adjustable ring, chain stitch, single crochet, double crochet and crab stitch..

Finished Size

9.5 inches tall



Copyright Information

This pattern and images are legal properties of DeliciousCrochet, are protected under international copyright laws and are intended for PERSONAL USE only. Other uses are strictly prohibited. All rights reserved.

This means you may not sell the pattern or share it in any format and under any circumstances, or distribute it (full or partially), or post it on the Internet, or translate it into other languages with the intent of reselling it or distributing it, or sell the finished toys based in this patterns (including derivative work) or the intellectual idea. For more information, please visit DeliciousCrochet.com

Realization

Head and chest:

The head and chest are crocheted in a single piece from top to bottom.



To avoid a hole at the beginning of your project, you need to start it with a double adjustable ring (loop twice the yarn on your finger and when you finish the round pull the remaining yarn to close the hole):

British racing green:

Rnd 1: 6 single crochet stitches.

Rnd 2: 2 single crochet in each stitch from last round (12 stitches).

Rnd 3: *1 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (18 stitches).

Rnd 4: Single crochet in each stitch through back loops only.

Rnd 5 to 9: Single crochet in each stitch.

Rnd 10: Through front loops only crochet: *2 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (24 stitches).

Rnd 11: *3 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (30 single crochet).

Switch to orange color:

Rnd 12: *4 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (36 stitches).

Rnd 13: *5 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (42 stitches).

Rnd 14: *6 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (48 stitches).

Rnd 15: *7 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (54 stitches).

Rnd 16: *8 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (60 stitches).

Rnd 17: Single crochet in each stitch.

Rnd 18: *9 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (66 stitches).

Rnd 19: Single crochet in each stitch.

Rnd 20: *10 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (72 stitches).

Rnd 21 to 30: Single crochet in each stitch.

Rnd 31: *10 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (total 66 puntos).

Rnd 32: Single crochet in each stitch.

Rnd 33: *9 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (60 stitches).

Rnd 34: Single crochet in each stitch.

Rnd 35: *8 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (54 stitches).

Rnd 36: *7 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (48 stitches).

Rnd 37: *6 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (42 stitches).

Rnd 38: *5 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (36 stitches).

Rnd 39: *4 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (30 stitches).

Rnd 40: *3 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (24 stitches).

Since next round you will start crocheting the chest, interspersing 2 single crochet rounds in green color and 1 in red color. Switch to green color and crochet:

Rnd 41 & 42: Single crochet in each stitch.

Switch to red color:

Rnd 43: *3 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (30 stitches).

Switch to green color:

Rnd 44 & 45: Single crochet in each stitch.

Switch to red color:

Rnd 46: *4 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (36 stitches).

Switch to green color:

Rnd 47 & 48: Single crochet in each stitch.

Switch to red color:

Rnd 49: *5 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (42 stitches).

Switch to green color:

Rnd 50 & 51: Single crochet in each stitch.

Switch to red color:

Rnd 52: *6 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (48 stitches).

Switch to green color:

Rnd 53 & 54: Single crochet in each stitch.

Make a knot, cut the yarn with scissors and fill with stuffing.

Pants (blue color):

The pants are crocheted from bottom to top, starting on the legs.

Into a double adjustable ring crochet:

Rnd 1: 6 single crochet stitches.

Rnd 2: 2 single crochet in each stitch from last round (12 stitches).

Rnd 3: *1 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (18 stitches).

Rnd 4: *2 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (24 stitches).

Rnd 5: Single crochet in each stitch.

Rnd 6: *3 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (30 stitches).

Rnd 7 & 8: Single crochet in each stitch.

Rnd 9: Single crochet in each stitch through back loops only.

Rnd 10: Single crochet in each stitch.

Rnd 11: Single crochet in each stitch through back loops only.

Rnd 12: Single crochet in each stitch.

Rnd 13: Single crochet in each stitch through back loops only.

Rnd 14 & 15: Single crochet in each stitch.

Make a knot and cut the yarn with scissors. Crochet the other leg following the above directions. Once you've finished round 15 of the second leg, without cutting the yarn off, join both legs together with 6 single crochet (crotch) and then continue crocheting the pants around the legs:

Rnd 1: 52 single crochet stitches.

Rnd 2 to 6: Single crochet in each stitch.

Rnd 7: *11 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 4 times (48 stitches).

Rnd 8: Single crochet in each stitch.

Make a knot and cut the yarn with scissors.

Double border of straw - Pants:

The double border of straw is directly crocheted on the legs, across rounds 9 and 11. In order to do so, just insert your hook on the front loops of each of those two rounds and crochet as following: *2 single crochet, 1 foundation chain of 6 stitches and 1 single crochet row on it* repeat from *to* till the end of the round, closing it with as slip stitch.

Make a knot and cut the yarn with scissors.

Pant legs:

The pant legs are crocheted directly on the legs. In order to do so, just insert your hook on the front loops of round 13 and crochet:


Rnd 1: *4 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (36 stitches).

Rnd 2 to 7: Single crochet in each stitch.

Make a knot, cut the yarn with scissors and fill the pants with stuffing.

Sew the pants and chest together by their openings.

Thread a tapestry needle with orange yarn, putting the yarn double, and make long stitches from the pumpkin's bottom (round 40) to the base of stem (round 12), pulling it a bit and making a knot to keep it secure. Repeat this procedure 6 times in order to get 6 ribs, as in the final project.



Eyes (black color):

Make 2. Into a double adjustable ring crochet:



Rnd 1: 6 single crochet stitches.

Rnd 2: Single crochet in each stitch.

Rnd 3: 2 single crochet in each stitch from last round (12 stitches).

Rnd 4: Single crochet in each stitch.

Rnd 5: *1 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (18 stitches).

Rnd 6: Single crochet in each stitch.

Join the borderline together with a single crochet row of 9 stitches. Make a knot and cut the yarn with scissors.

Sew the eyes over the pumpkin front side. With black yarn embroider the nose, as a small triangle, and the mouth with a little

tooth on the side. With white yarn embroider the inside details of the eyes, nose and mouth, as you can see in the image.

Shoes (terracotta color):

Make 2. Work a foundation chain of 16 stitches (do not close them into a circle) and crochet around them:

Rnd 1: 2 single crochet in first stitch, 14 single crochet, 4 single crochet in next stitch, 14 single crochet, 2 single crochet in next stitch (36 stitches)

Rnd 2: *1 single crochet, 2 single crochet in next stitch, 15 single crochet, 2 single crochet in next stitch * repeat from *to* twice (40 stitches).

Rnd 3: *2 single crochet, 2 single crochet in next stitch, 16 single crochet, 2 single crochet in next stitch * repeat from *to* twice (44 stitches).

Rnd 4 to 7: Single crochet in each stitch.

Rnd 8: 12 single crochet, *1 decrease (2 single crochet closed together), 1 single crochet* repeat from *to* 7 times, 1 decrease, 9 single crochet (36 stitches).

Rnd 9: 13 single crochet, 1 decrease (2 single crochet closed together), 1 single crochet, 1 double decrease (3 single crochet closed together), 2 single crochet, 1 double decrease, 1 single crochet, 1 decrease, 9 single crochet (30 stitches).

Rnd 10: Single crochet in each stitch.

Rnd 11: *3 single crochet, 1 decrease (2 single crochet closed together)*, repeat from *to* 6 times (24 stitches).

Rnd 12 to 14: Single crochet in each stitch.

Make a knot, cut the yarn with scissors and fill with stuffing.

Sew the shoes, by their openings, to round 5 of pants.



Arms (Make 2):

The arms are crocheted from top to bottom, interspersing 2 green single crochet rounds and 1 red single crochet round. Into a double adjustable ring crochet:

Green color:

Rnd 1: 6 single crochet stitches.

Rnd 2: 2 single crochet in each stitch from last round (12 stitches).

Switch to red color:

Rnd 3: Single crochet in each stitch.

Switch to green color:

Rnd 4 & 5: Single crochet in each stitch.

Switch to red color:

Rnd 6: Single crochet in each stitch.



Switch to green color:

Rnd 7: *5 single crochet, 2 single crochet in next stitch*, repeat from *to* twice (14 stitches).

Rnd 8: Single crochet in each stitch.

Switch to red color:

Rnd 9: Single crochet in each stitch.

Switch to green color:

Rnd 10 & 11: Single crochet in each stitch.

Switch to red color:

Rnd 12: *6 single crochet, 2 single crochet in next stitch*, repeat from *to* twice (16 stitches).

Switch to green color:

Rnd 13 & 14: Single crochet in each stitch.

Switch to red color:

Rnd 15: Single crochet in each stitch.

Switch to green color:

Rnd 16: Single crochet in each stitch.

Rnd 17: Double crochet in each stitch through front loops only.

Make a knot, cut the yarn with scissors and fill with stuffing.

Hands (terracotta color):

Make 2. Into a double adjustable ring crochet:

Rnd 1: 6 single crochet stitches.

Rnd 2: 2 single crochet in each stitch from last round (12 stitches).

Rnd 3: *1 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (18 stitches).

Rnd 4 & 5: Single crochet in each stitch.

Rnd 6: 9 single crochet, 5 double crochet closed together in next stitch, 8 single crochet (18 stitches).

Rnd 7: *7 single crochet, 1 decrease (2 single crochet closed together)* repeat from *to* twice (16 stitches).

Rnd 8 & 9: Single crochet in each stitch.

Rnd 10 & 11: Single crochet in each stitch through back loops only.



Make a knot and cut the yarn with scissors.

Double border of straw - Hands:




The double border of straw is directly crocheted on the hands, across rounds 10 and 11. In order to do so, just insert your hook on the front loops of each of those two rounds and crochet as following: *2 single crochet, 1 foundation chain of 4 stitches and 1 single crochet row on it* repeat from *to* till the end of the rounds.

Make a knot, cut the yarn with

scissors and fill the hands with stuffing.

Sew the arms and hands together by their openings, making the stitches from the back loops of round 16 of the arms in order to get the cuffs over the hands.

In order to assemble the arms to the body, first thread a tapestry needle with red yarn and make a stitch in the inner side of the arm, on round 3. Then, pass the needle through the chest from side to side on round



43, which is the first red round of the chest, pulling it tight in order to get the arm jointed to the body (do it twice to keep the union firm). Repeat this procedure for the other arm.



Bib front (blue color):

Work a foundation chain of 8 stitches (do not close them into a circle) and crochet around:

Rnd 1: 16 single crochet stitches.

Rnd 2 to 10: Single crochet in each stitch.

Crochet 2 extra single crochet stitches, and then, join the borderline together with a single crochet row of 8 stitches. Make a knot and cut the yarn with scissors.

Sew the bib front by its inferior border over the union between the chest and pants, on the front side of the body.

Shoulder straps (blue color):

Make 2. Work a foundation chain of 28 stitches (do not close them into a circle) and crochet around:

Rnd 1: 27 single crochet, 3 single crochet in next stitch, 26 single crochet, 2 single crochet in next stitch (58 stitches). Make a knot and cut the yarn with scissors.

Sew the shoulder straps by their endings, crossing them on the back side of the body. With brown yarn embroider a french knot over the straps front ending as buttons.

Hat (brown color):

Into a double adjustable ring crochet:

Rnd 1: 6 single crochet stitches.

Rnd 2: 2 single crochet in each stitch from last round (12 stitches).

Rnd 3: *1 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (18 stitches).

Rnd 4: 1 single crochet, *2 single crochet in next stitch, 2 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 1 single crochet (24 stitches).

Rnd 5: *2 single crochet in first stitch, 3 single crochet* repeat from *to* 6 times (30 stitches).

Rnd 6: 2 single crochet, *2 single crochet in next stitch, 4 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 2 single crochet (36 stitches).

Rnd 7: *5 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (42 stitches).

Rnd 8: 2 single crochet, *2 single crochet in next stitch, 6 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 4 single crochet (48 stitches).

Rnd 9: 3 single crochet, * 2 single crochet in next stitch, 7 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 4 single crochet (54 stitches).

Rnd 10: *2 single crochet in first stitch, 8 single crochet* repeat from *to* 6 times (60 stitches).

Rnd 11: 1 single crochet, *2 single crochet in next stitch, 9 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 8 single crochet (66 stitches).

Rnd 12: 4 single crochet, *2 single crochet in next stitch, 10 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 6 single crochet (72 stitches).

Rnd 13: Single crochet in each stitch through back loops only.

Rnd 14 to 18: Single crochet in each stitch.

Rnd 19: Work the first 50 stitches in single crochet through front loops only, and then, complete the round in regular single crochet.

Rnd 20: Single crochet in each stitch.



Rnd 21: Work the first 50 stitches in single crochet through front loops only, and then, complete the round in regular single crochet.

Rnd 22: Through front loops only crochet: 7 single crochet,*2 single crochet in next stitch, 11 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 4 single crochet (78 stitches).

Rnd 23: *12 single crochet, 2 single crochet in next stitch*, repeat from *to* 6 times (84 stitches).

Rnd 24: 2 single crochet,*2 single crochet in next stitch, 13 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 11 single crochet (90 stitches).

Rnd 25: 8 single crochet,*2 single crochet in next stitch, 14 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 6 single crochet (96 stitches).

Rnd 26: *2 single crochet in first stitch, 15 single crochet* repeat from *to* 6 times (102 stitches).

Rnd 27: 5 single crochet,*2 single crochet in next stitch, 16 single crochet* repeat from *to* 5 times, 2 single crochet in next stitch, 11 single crochet (108 stitches).

Rnd 28: *2 single crochet in first stitch, 17 single crochet* repeat from *to* 6 times (114 stitches).

Rnd 29: Crab stitch in each stitch.

Make a knot and cut the yarn with scissors.



Double border of straw - Hat:

The double border of straw is directly crocheted on the hat, across the back loops of the 50 stitches you worked through front loops only, on rounds 19 and 21. In order to do so, with the wrong side of the hat facing you, insert your hook on the front loops of each of those 50 stitches and crochet as following: *2 single crochet, 1 foundation chain of 12 stitches and 1 single crochet row on it* repeat from *to* till complete both rows.

Make a knot and cut the yarn with scissors.

Place the hat over the scarecrow's head, placing the straw border on the sides and back of the head.

Ending details

Sew the pants and chest together by their openings.

Thread a tapestry needle with orange yarn, putting the yarn double, and make long stitches from the pumpkin's bottom (round 40) to the base of stem (round 12), pulling it a bit and making a knot to keep it secure. Repeat this procedure 6 times in order to get 6 ribs, as in the final project.

Sew the eyes over the pumpkin front side. With black yarn embroider the nose, as a small triangle, and the mouth with a little tooth on the side. With white yarn embroider the inside details of the eyes, nose and mouth.

Sew the shoes, by their openings, to round 5 of pants.

Sew the arms and hands together by their openings, making the stitches from the back loops of round 16 of the arms in order to get the cuffs over the hands.

In order to assemble the arms to the body, first thread a tapestry needle with red yarn and make a stitch in the inner side of the arm, on round 3. Then, pass the needle through the chest from side to side on round 43, which is the first red round of the chest, pulling it tight in order to get the arm jointed to the body (do it twice to keep the union firm). Repeat this procedure for the other arm.

Sew the bib front by its inferior border over the union between the chest and pants, on the front side of the body.

Sew the shoulder straps by their endings, crossing them on the back side of the body. With brown yarn embroider a french knot over the straps front ending as buttons.

Place the hat over the scarecrow's head, placing the straw border on the sides and back of the head.

Enjoy!

Paola Navarro

www.deliciouscrochet.com

Tucumán - ARGENTINA